



Configuration Fields

B2B Quote Documentation

Guide for Magento administrators, technical project owners, and implementation teams.

LAST UPDATED
2026-10-13

SOURCE
[Open this article online](#)

EXTENSION
[Magento 2 Extension B2B Quote](#)

Configuration Fields

This reference lists the Magento Admin settings exposed by the base package and its documented add-ons: `mageb2b/b2b-quote`, `mageb2b/b2b-quote-importexport`, `mageb2b/b2b-quote-opensign`.

Configuration paths are included for controlled deployments and `config:set`. Use Magento Admin for normal changes so field validation and scope inheritance still apply. The extension status display is not listed because it reports installation state rather than a configurable value.

mageb2b/b2b-quote

General Settings

Field	Configuration path	Input	Scope
Enable B2B Quote	<code>b2bquote/general/enable</code>	Select	Default, Website, Store view
Quote Number Format	<code>b2bquote/general/quote_number_format</code>	Text	Default, Website, Store view
Default Quote Status	<code>b2bquote/general/default_status</code>	Select	Default, Website, Store view
Default Expiration Days	<code>b2bquote/general/default_expiration_days</code>	Text	Default, Website, Store view
Accept Mode	<code>b2bquote/general/accept_mode</code>	Select	Default, Website, Store view
Allow Customer to Choose Accept Mode	<code>b2bquote/general/allow_quote_accept_mode_choice</code>	Select	Default, Website, Store view
Maximum Quotes Per Customer	<code>b2bquote/general/max_quotes_per_customer</code>	Text	Default, Website, Store view
Maximum Quote Items	<code>b2bquote/general/max_quote_items</code>	Text	Default, Website, Store view
Maximum Item Quantity	<code>b2bquote/general/max_item_qty</code>	Text	Default, Website, Store view

Field	Configuration path	Input	Scope
Allowed Customer Groups	<code>b2bquote/general/allowed_customer_groups</code>	Multi-select	Default, Website, Store view
Enable Auto-Approval	<code>b2bquote/general/auto_approval_enabled</code>	Select	Default, Website, Store view
Auto-Approval Threshold	<code>b2bquote/general/auto_approval_threshold</code>	Text	Default, Website, Store view
Clear Cart After Conversion	<code>b2bquote/general/clear_cart_after_conversion</code>	Select	Default, Website, Store view
Clear Cart Before Accepting Quote to Cart	<code>b2bquote/general/clear_cart_before_accept_add_to_cart</code>	Select	Default, Website, Store view

Visibility dependencies:

- `b2bquote/general/default_status` is available when `b2bquote/general/enable` is 1.
- `b2bquote/general/default_expiration_days` is available when `b2bquote/general/enable` is 1.
- `b2bquote/general/accept_mode` is available when `b2bquote/general/enable` is 1.
- `b2bquote/general/accept_mode` is available when `b2bquote/general/allow_quote_accept_mode_choice` is 0.
- `b2bquote/general/allow_quote_accept_mode_choice` is available when `b2bquote/general/enable` is 1.
- `b2bquote/general/max_quotes_per_customer` is available when `b2bquote/general/enable` is 1.
- `b2bquote/general/max_quote_items` is available when `b2bquote/general/enable` is 1.
- `b2bquote/general/max_item_qty` is available when `b2bquote/general/enable` is 1.
- `b2bquote/general/allowed_customer_groups` is available when `b2bquote/general/enable` is 1.
- `b2bquote/general/auto_approval_enabled` is available when `b2bquote/general/enable` is 1.
- `b2bquote/general/auto_approval_threshold` is available when `b2bquote/general/enable` is 1.
- `b2bquote/general/auto_approval_threshold` is available when `b2bquote/general/auto_approval_enabled` is 1.

- `b2bquote/general/clear_cart_after_conversion` is available when `b2bquote/general/enable` is 1.
- `b2bquote/general/clear_cart_before_accept_add_to_cart` is available when `b2bquote/general/enable` is 1.
- `b2bquote/general/clear_cart_before_accept_add_to_cart` is available when `b2bquote/general/accept_mode` is `add_to_cart`.

Admin Responsibility

Field	Configuration path	Input	Scope
Admin User Quote	<code>b2bquote/admin_assignment/mode</code>	Select	Default, Website, Store view
Enable Admin Inbox Notifications	<code>b2bquote/admin_assignment/admin_inbox_enabled</code>	Select	Default, Website, Store view

Guest Quote Settings

Field	Configuration path	Input	Scope
Enable Guest Quotes	<code>b2bquote/guest_quote/enabled</code>	Select	Default, Website, Store view
Quote Number Format	<code>b2bquote/guest_quote/quote_number_format</code>	Text	Default, Website, Store view
Access Token Pattern	<code>b2bquote/guest_quote/access_token_pattern</code>	Text	Default, Website, Store view

Visibility dependencies:

- `b2bquote/guest_quote/enabled` is available when `b2bquote/general/enable` is 1.
- `b2bquote/guest_quote/quote_number_format` is available when `b2bquote/guest_quote/enabled` is 1.
- `b2bquote/guest_quote/access_token_pattern` is available when `b2bquote/guest_quote/enabled` is 1.

PDF Settings

Field	Configuration path	Input	Scope
PDF Layout	b2bquote/pdf/pdf_layout	Custom control	Default, Website, Store view
PDF Company Logo	b2bquote/pdf/pdf_logo_path	Image	Default, Website, Store view
PDF Company Name	b2bquote/pdf/pdf_company_name	Text	Default, Website, Store view
PDF Company Address	b2bquote/pdf/pdf_company_address	Text area	Default, Website, Store view
PDF Company Phone	b2bquote/pdf/pdf_company_phone	Text	Default, Website, Store view
PDF Company Email	b2bquote/pdf/pdf_company_email	Text	Default, Website, Store view
PDF Footer Text	b2bquote/pdf/pdf_footer_text	Text area	Default, Website, Store view
PDF Download Restricted Statuses	b2bquote/pdf/pdf_download_restricted_statuses	Multi-select	Default, Website, Store view
Display Quote Item Notes	b2bquote/pdf/pdf_display_item_notes	Select	Default, Website, Store view

Frontend Settings

Field	Configuration path	Input	Scope
Add to Quote Button Text	b2bquote/frontend_settings/button_text	Text	Default, Website, Store view

Field	Configuration path	Input	Scope
Display on Product Page	b2bquote/frontend_settings/display_on_product	Select	Default, Website, Store view
Display on Category Page	b2bquote/frontend_settings/display_on_category	Select	Default, Website, Store view
Show in Top Navigation	b2bquote/frontend_settings/show_in_topnav	Select	Default, Website, Store view
Enable Mini Quote	b2bquote/frontend_settings/enable_mini_quote	Select	Default, Website, Store view
Mini Quote Max Quotes	b2bquote/frontend_settings/mini_quote_max_display	Text	Default, Website, Store view
Mini Quote Display Mode	b2bquote/frontend_settings/mini_quote_display_mode	Select	Default, Website, Store view
Allow Counter Offer	b2bquote/frontend_settings/allow_counter_offer	Select	Default, Website, Store view
Show Prices in Frontend	b2bquote/frontend_settings/show_prices	Select	Default, Website, Store view
Quote List Page Size	b2bquote/frontend_settings/quote_list_page_size	Text	Default, Website, Store view
Redirect to Quote After Product Add	b2bquote/frontend_settings/redirect_after_product_add	Select	Default, Website, Store view
Enable Cart to Quote Conversion	b2bquote/frontend_settings/enable_cart_conversion	Select	Default, Website, Store view
Cart Conversion Minimum Amount	b2bquote/frontend_settings/cart_conversion_min_amount	Text	Default, Website, Store view
Cart Conversion Button Text	b2bquote/frontend_settings/cart_conversion_button_text	Text	Default, Website, Store view

Field	Configuration path	Input	Scope
Show History Tab	<code>b2bquote/frontend_settings/show_history_tab</code>	Select	Default, Website, Store view
Allow Duplicate Quote	<code>b2bquote/frontend_settings/allow_duplicate_quote</code>	Select	Default, Website, Store view
Duplicate Quote: Copy Fields	<code>b2bquote/frontend_settings/duplicate_copy_fields</code>	Multi-select	Default, Website, Store view

Visibility dependencies:

- `b2bquote/frontend_settings/mini_quote_max_display` is available when `b2bquote/frontend_settings/enable_mini_quote` is 1.
- `b2bquote/frontend_settings/mini_quote_display_mode` is available when `b2bquote/frontend_settings/enable_mini_quote` is 1.
- `b2bquote/frontend_settings/cart_conversion_min_amount` is available when `b2bquote/frontend_settings/enable_cart_conversion` is 1.
- `b2bquote/frontend_settings/cart_conversion_button_text` is available when `b2bquote/frontend_settings/enable_cart_conversion` is 1.
- `b2bquote/frontend_settings/duplicate_copy_fields` is available when `b2bquote/frontend_settings/allow_duplicate_quote` is 1.

Email Notifications

Field	Configuration path	Input	Scope
Enable Email Notifications	<code>b2bquote/email_notifications/enabled</code>	Select	Default, Website, Store view
Email Sender	<code>b2bquote/email_notifications/email_sender</code>	Select	Default, Website, Store view
Admin Recipients	<code>b2bquote/email_notifications/admin_recipients</code>	Text	Default, Website, Store view
Status Changed Template	<code>b2bquote/email_notifications/template_status_changed</code>	Select	Default, Website, Store view
Quote Expired Template	<code>b2bquote/email_notifications/template_quote_expired</code>	Select	Default, Website, Store view
Message Notification Template	<code>b2bquote/email_notifications/template_message_notification</code>	Select	Default, Website, Store view

Field	Configuration path	Input	Scope
Message Notification Template (Admin → Customer)	<code>b2bquote/email_notifications/template_message_notification_admin</code>	Select	Default, Website, Store view
Send Email Copy Method	<code>b2bquote/email_notifications/email_copy_method</code>	Select	Default, Website, Store view
Expiration Reminder Intervals	<code>b2bquote/email_notifications/expiration_reminder_intervals</code>	Custom control	Default, Website, Store view
Enable Expiration Reminder Emails	<code>b2bquote/email_notifications/expiration_reminder_enabled</code>	Select	Default, Website, Store view
Expiration Reminder Template	<code>b2bquote/email_notifications/template_expiration_reminder</code>	Select	Default, Website, Store view
Attach Quote PDF	<code>b2bquote/email_notifications/attach_quote_pdf</code>	Select	Default, Website, Store view
Attach Customer Files	<code>b2bquote/email_notifications/attach_customer_files</code>	Select	Default, Website, Store view

Visibility dependencies:

- `b2bquote/email_notifications/email_sender` is available when `b2bquote/email_notifications/enabled` is 1.
- `b2bquote/email_notifications/admin_recipients` is available when `b2bquote/email_notifications/enabled` is 1.
- `b2bquote/email_notifications/template_status_changed` is available when `b2bquote/email_notifications/enabled` is 1.
- `b2bquote/email_notifications/template_quote_expired` is available when `b2bquote/email_notifications/enabled` is 1.
- `b2bquote/email_notifications/template_message_notification` is available when `b2bquote/email_notifications/enabled` is 1.
- `b2bquote/email_notifications/template_message_notification_admin` is available when `b2bquote/email_notifications/enabled` is 1.
- `b2bquote/email_notifications/email_copy_method` is available when `b2bquote/email_notifications/enabled` is 1.
- `b2bquote/email_notifications/expiration_reminder_intervals` is available when `b2bquote/email_notifications/enabled` is 1.
- `b2bquote/email_notifications/expiration_reminder_enabled` is available when `b2bquote/email_notifications/enabled` is 1.
- `b2bquote/email_notifications/template_expiration_reminder` is available when `b2bquote/email_notifications/enabled` is 1.

- `b2bquote/email_notifications/attach_quote_pdf` is available when `b2bquote/email_notifications/enabled` is 1.
- `b2bquote/email_notifications/attach_customer_files` is available when `b2bquote/email_notifications/enabled` is 1.

Email templates for individual status changes are selected per transition in the transition form's `notification_template` (**Email Template**) field, not through a configuration field. See [Status Transitions](#).

Pricing Settings

Field	Configuration path	Input	Scope
Enable Price Negotiation	<code>b2bquote/pricing/negotiation_enabled</code>	Select	Default, Website, Store view

Quote Fees

Field	Configuration path	Input	Scope
Apply Tax to Quote Fee	<code>b2bquote/quote_fee/apply_tax</code>	Select	Default, Website, Store view
Fee Amount Includes Tax	<code>b2bquote/quote_fee/fee_includes_tax</code>	Select	Default, Website, Store view
Tax Class	<code>b2bquote/quote_fee/tax_class_id</code>	Select	Default, Website, Store view

Visibility dependencies:

- `b2bquote/quote_fee/fee_includes_tax` is available when `b2bquote/quote_fee/apply_tax` is 1.
- `b2bquote/quote_fee/tax_class_id` is available when `b2bquote/quote_fee/apply_tax` is 1.

Shipping Settings

Field	Configuration path	Input	Scope
Shipping Required	<code>b2bquote/shipping/required</code>	Select	Default, Website, Store view

Field	Configuration path	Input	Scope
Free Shipping Threshold	<code>b2bquote/shipping/free_shipping_threshold</code>	Text	Default, Website, Store view
Disallowed Shipping Methods	<code>b2bquote/shipping/disallowed_methods</code>	Multi-select	Default, Website, Store view

Payment Settings

Field	Configuration path	Input	Scope
Payment Required	<code>b2bquote/payment/required</code>	Select	Default, Website, Store view
Disallowed Payment Methods	<code>b2bquote/payment/disallowed_methods</code>	Multi-select	Default, Website, Store view

Attachments

Field	Configuration path	Input	Scope
Allowed File Extensions	<code>b2bquote/attachments/allowed_extensions</code>	Text	Default, Website, Store view
Max File Size (MB)	<code>b2bquote/attachments/max_filesize_mb</code>	Text	Default, Website, Store view
Max Attachments (Frontend)	<code>b2bquote/attachments/max_attachments_frontend</code>	Text	Default, Website, Store view
Disable Attachments for Statuses	<code>b2bquote/attachments/disabled_statuses</code>	Multi-select	Default, Website, Store view
Temporary File Retention (Hours)	<code>b2bquote/attachments/temporary_file_retention_hours</code>	Text	Default

Messaging

Field	Configuration path	Input	Scope
Maximum Message Length	<code>b2bquote/messaging/max_message_length</code>	Text	Default, Website, Store view
Disable Messaging for Statuses	<code>b2bquote/messaging/messaging_disabled_statuses</code>	Multi-select	Default, Website, Store view

Inventory Reservation

Field	Configuration path	Input	Scope
Reserve Inventory on Approval	<code>b2bquote/inventory/reserve_on_approval</code>	Select	Default, Website, Store view
Reservation Compensation Code	<code>b2bquote/inventory/reservation_compensation_code</code>	Text	Default, Website, Store view
Release Inventory on Expiration	<code>b2bquote/inventory/release_on_expiration</code>	Select	Default, Website, Store view
Release Inventory on Rejection	<code>b2bquote/inventory/release_on_rejection</code>	Select	Default, Website, Store view
Release Inventory on Order Creation	<code>b2bquote/inventory/release_on_order_creation</code>	Select	Default, Website, Store view

Visibility dependencies:

- `b2bquote/inventory/reservation_compensation_code` is available when `b2bquote/inventory/reserve_on_approval` is `1`.
- `b2bquote/inventory/release_on_expiration` is available when `b2bquote/inventory/reserve_on_approval` is `1`.
- `b2bquote/inventory/release_on_rejection` is available when `b2bquote/inventory/reserve_on_approval` is `1`.
- `b2bquote/inventory/release_on_order_creation` is available when `b2bquote/inventory/reserve_on_approval` is `1`.

Pricing Rules

Field	Configuration path	Input	Scope
Enable Pricing Rules	<code>b2bquote/pricing_rules/pricing_rules_enabled</code>	Select	Default, Website, Store view
Allow Rule Stacking	<code>b2bquote/pricing_rules/can_stack_rules</code>	Select	Default, Website, Store view

Visibility dependencies:

- `b2bquote/pricing_rules/can_stack_rules` is available when `b2bquote/pricing_rules/pricing_rules_enabled` is 1.

Quote Merge & Split

Field	Configuration path	Input	Scope
Enable Quote Merge (Frontend)	<code>b2bquote/quote_merge_split/merge_enabled</code>	Select	Default, Website, Store view
Merge Messages Default	<code>b2bquote/quote_merge_split/merge_messages_default</code>	Select	Default, Website, Store view
Merge Attachments Default	<code>b2bquote/quote_merge_split/merge_attachments_default</code>	Select	Default, Website, Store view
Enable Quote Split (Frontend)	<code>b2bquote/quote_merge_split/split_enabled</code>	Select	Default, Website, Store view
Delete Source Quotes After Merge	<code>b2bquote/quote_merge_split/delete_source_after_merge</code>	Select	Default, Website, Store view

Visibility dependencies:

- `b2bquote/quote_merge_split/merge_enabled` is available when `b2bquote/general/enable` is 1.
- `b2bquote/quote_merge_split/merge_messages_default` is available when `b2bquote/quote_merge_split/merge_enabled` is 1.
- `b2bquote/quote_merge_split/merge_attachments_default` is available when `b2bquote/quote_merge_split/merge_enabled` is 1.
- `b2bquote/quote_merge_split/split_enabled` is available when `b2bquote/general/enable` is 1.

- `b2bquote/quote_merge_split/delete_source_after_merge` is available when `b2bquote/quote_merge_split/merge_enabled` is 1.

Workflow

Field	Configuration path	Input	Scope
Enable Workflow	<code>b2bquote/workflow/workflow_enabled</code>	Select	Default, Website, Store view
Workflow Rules Validate Transitions	<code>b2bquote/workflow/transition_validation</code>	Select	Default, Website, Store view

Visibility dependencies:

- `b2bquote/workflow/transition_validation` is available when `b2bquote/workflow/workflow_enabled` is 1.

Revision Tracking

Field	Configuration path	Input	Scope
Enabled Revision Events	<code>b2bquote/revision/enabled_events</code>	Multi-select	Default, Website, Store view
Enable Revision Cleanup	<code>b2bquote/revision/cleanup_enabled</code>	Select	Default, Website, Store view
Revision Retention Days	<code>b2bquote/revision/cleanup_days</code>	Text	Default, Website, Store view

Visibility dependencies:

- `b2bquote/revision/cleanup_days` is available when `b2bquote/revision/cleanup_enabled` is 1.

Customer Experience Settings

Field	Configuration path	Input	Scope
Use Customer Address Book	<code>b2bquote/customer_experience/use_customer_addressbook</code>	Select	Default, Website, Store view

Field	Configuration path	Input	Scope
Allow Empty Draft Quote	b2bquote/customer_experience/allow_empty_draft_quote	Select	Default, Website, Store view
Draft Quote Lifetime (Days)	b2bquote/customer_experience/draft_lifetime_days	Text	Default, Website, Store view
Draft Deletion Notice (Days Before)	b2bquote/customer_experience/draft_notice_days_before	Text	Default, Website, Store view
Typical Response Time (Business Days)	b2bquote/customer_experience/typical_response_time_days	Text	Default, Website, Store view
Important Information (WYSIWYG)	b2bquote/customer_experience/important_information	Custom control	Default, Website, Store view
Approval Validity Period (Days)	b2bquote/customer_experience/approval_validity_days	Text	Default, Website, Store view

Order Creation Settings

Field	Configuration path	Input	Scope
Price Change Behavior	b2bquote/order_creation/price_change_behavior	Select	Default, Website, Store view
Stock Validation Behavior	b2bquote/order_creation/stock_validation_behavior	Select	Default, Website, Store view
Check Product Availability	b2bquote/order_creation/product_availability_check	Select	Default, Website, Store view

mageb2b/b2b-quote-importexport

Import and Export

Field	Configuration path	Input	Scope
Export Guest Access Tokens	<code>b2bquote/import_export/export_access_tokens</code>	Select	Default

Guest access tokens are not exported by default; the `access_token` column is exported empty. Enable this only when guest quote links must be transferred to another trusted installation.

mageb2b/b2b-quote-opensign

OpenSign Digital Signatures

Field	Configuration path	Input	Scope
Enable Digital Signatures	<code>b2bquote/opensign/enabled</code>	Select	Default, Website
OpenSign API URL	<code>b2bquote/opensign/api_url</code>	Text	Default
Application ID	<code>b2bquote/opensign/app_id</code>	Text	Default
Master Key	<code>b2bquote/opensign/master_key</code>	Protected text	Default
Session Token	<code>b2bquote/opensign/session_token</code>	Protected text	Default
System User ID	<code>b2bquote/opensign/system_user_id</code>	Text	Default
System Contracts User ID	<code>b2bquote/opensign/system_contracts_user_id</code>	Text	Default
Webhook Secret	<code>b2bquote/opensign/webhook_secret</code>	Protected text	Default
Require Signature for Acceptance	<code>b2bquote/opensign/require_signature</code>	Select	Default, Website
Signature Request Expiry (Days)	<code>b2bquote/opensign/expiry_days</code>	Text	Default, Website
OpenSign Public URL	<code>b2bquote/opensign/public_url</code>	Text	Default

Field	Configuration path	Input	Scope
Test Connection	<code>b2bquote/opensign/test_connection</code>	Custom control	Default

Visibility dependencies:

- `b2bquote/opensign/api_url` is available when `b2bquote/opensign/enabled` is `1`.
- `b2bquote/opensign/app_id` is available when `b2bquote/opensign/enabled` is `1`.
- `b2bquote/opensign/master_key` is available when `b2bquote/opensign/enabled` is `1`.
- `b2bquote/opensign/session_token` is available when `b2bquote/opensign/enabled` is `1`.
- `b2bquote/opensign/system_user_id` is available when `b2bquote/opensign/enabled` is `1`.
- `b2bquote/opensign/system_contracts_user_id` is available when `b2bquote/opensign/enabled` is `1`.
- `b2bquote/opensign/webhook_secret` is available when `b2bquote/opensign/enabled` is `1`.
- `b2bquote/opensign/require_signature` is available when `b2bquote/opensign/enabled` is `1`.
- `b2bquote/opensign/expiry_days` is available when `b2bquote/opensign/enabled` is `1`.
- `b2bquote/opensign/public_url` is available when `b2bquote/opensign/enabled` is `1`.
- `b2bquote/opensign/test_connection` is available when `b2bquote/opensign/enabled` is `1`.