



Configuration

Bulkgood Shipping

Guide for Magento administrators, technical project owners, and implementation teams.

LAST UPDATED
2026-09-20

SOURCE
[Open this article online](#)

EXTENSION
[Magento 2 Extension Bulkgood](#)

Configuration

Open **Stores > Configuration > Sales > Shipping Methods > Table Rates**.

Configure Magento's normal Table Rates fields first, then set the four Bulkgood options in the same section.

Configuration

ADVANCED

Antigua & Barbuda
Argentina

Show Method if Not Applicable (website) No

Sort Order (website)

Bulkgood Price Source Priority (store view)

Source	Action
Bulkgood Price / Product & Country	
Bulkgood Price / Product	
Table Rate	

Add Source Priority

Set the priority order for bulk pricing sources.

Price Calculation Method (store view) Sum

Choose how bulk prices are aggregated in the cart. Please note that the price calculation method will apply on the final selected type of bulkgood through the priority.

Calculate Bulkgood Price by Qty (store view) No

Enable or disable calculation of bulkgood price based on the quantity of items in the cart.

Enable Bulkgood Price Logging (store view) No

Enable or disable logging for bulkgood price calculations.

In-Store Delivery	
UPS	
USPS	

Bulkgood Price Source Priority

Add up to three sources and place them in the order in which they should be checked:

Source	Value used
Bulkgood Price / Product & Country	Country-specific product rows that match the shipping country and active Table Rates condition
Bulkgood Price / Product	The general Bulkgood Price stored on bulk products
Table Rate	The price from the matching Table Rates row with Bulkgood = 1

The first source with at least one usable value wins for the bulk calculation. This is a cart-level decision, not an individual fallback for each product. For example, if the country source is first and one of three bulk products has a matching country price, that source is selected. The two products without a country price are not then filled from the general product source.

For that reason, use a product source first only when the relevant products are priced consistently through that source.

Price Calculation Method

This setting combines values from the selected product source:

- **Sum** adds all available values.
- **Highest** uses the largest available value.
- **Lowest** uses the smallest available value.
- **Average** uses the arithmetic mean.

It does not combine ordinary and bulk table rates, and it does not change a single Table Rates price.

Calculate Bulkgood Price by Qty

When enabled, each country-specific or general product price is multiplied by that item's quantity before the calculation method runs. The option does not multiply the price returned by the Table Rates source.

Example with **Sum**:

Product	Price	Quantity	Contributing value
Storage cabinet	45.00	2	90.00
Workbench	70.00	1	70.00
Shipping price			160.00

Enable Bulkgood Price Logging

Enable this temporarily when a checkout result does not match your expectation. Entries are written through Magento's standard logger and normally appear in `var/log/system.log`. The log records the configured source order, product price candidates, selected source and final amount.

Disable it again after troubleshooting to avoid unnecessary log volume.

Scope

The four fields are available at default, website and store-view scope. Magento's Table Rates import and export is website-scoped, while the Bulkgood product attributes are website-scoped product values. Confirm both the configuration scope and the product website assignment before comparing storefront results.

A safe first configuration

The shipped defaults already enable all three price sources in the priority list, use **Highest** as the calculation method and multiply by quantity — the steps below

deliberately narrow that to a predictable starting point.

For a catalog in which every bulk product has a general freight price:

1. **Bulkgood Price / Product**
2. **Table Rate**

Use **Sum** if each product contributes freight, or **Highest** if the most expensive handling requirement should determine the charge. Import a broad **Bulkgood = 1** row for every served destination, even though the visible amount comes from the product.

For a centrally managed weight or subtotal matrix, place **Table Rate** first and manage the amount entirely in the CSV.

Configuration reference

Config path	Admin label
<code>carriers/ablerate/bulkgood_price_priority</code>	Bulkgood Price Source Priority
<code>carriers/ablerate/price_calculation_method</code>	Price Calculation Method
<code>carriers/ablerate/calculate_by_quantity</code>	Calculate Bulkgood Price by Qty
<code>carriers/ablerate/log_enabled</code>	Enable Bulkgood Price Logging

Continue with **your first bulkgood product** and the **Table Rates setup**.