



Configuration Fields

Customer ID

Guide for Magento administrators, technical project owners, and implementation teams.

LAST UPDATED
2026-08-29

SOURCE
[Open this article online](#)

EXTENSION
[Magento 2 Extension Customer ID](#)

Configuration Fields

This reference lists the settings exposed by `mageb2b/customer-id` in Magento Admin.

Configuration paths are included for controlled deployments and `config:set`. Use Magento Admin for normal changes so field validation and scope inheritance still apply. The extension status display is not listed because it reports installation state rather than a configurable value.

General settings

Field	Configuration path	Input	Scope
Login with Customer ID possible	<code>customer_id/customer_id/login</code>	Select	Default, Website, Store view
Auto increment for customer ID	<code>customer_id/customer_id/auto_increment</code>	Select	Default, Website, Store view
Auto template for customer ID	<code>customer_id/customer_id/id_template</code>	Text	Default, Website, Store view
Apply template also to already existing id's	<code>customer_id/customer_id/template_force_apply</code>	Select	Default, Website, Store view
Next number range	<code>customer_id/customer_id/next_increment</code>	Text	Default, Website, Store view
ID range is global	<code>customer_id/customer_id/idrange_global</code>	Select	Default, Website, Store view
List of characters, which should not be allowed	<code>customer_id/customer_id/disallowed_characters</code>	Text	Default, Website, Store view
Log Customer IDs while saving	<code>customer_id/customer_id/log_customerids</code>	Select	Default, Website, Store view
Display Customer ID on customer dashboard	<code>customer_id/customer_id/display_customer_id_on_customer_dashboard</code>	Select	Default, Website

Visibility dependencies:

- `customer_id/customer_id/id_template` is available when

`customer_id/customer_id/auto_increment` is 1.

- `customer_id/customer_id/template_force_apply` is available when `customer_id/customer_id/auto_increment` is 1.
- `customer_id/customer_id/next_increment` is available when `customer_id/customer_id/auto_increment` is 1.
- `customer_id/customer_id/idrange_global` is available when `customer_id/customer_id/auto_increment` is 1.