



Configuration Fields

Workflow

Guide for Magento administrators, technical project owners, and implementation teams.

LAST UPDATED
2026-08-29

SOURCE
[Open this article online](#)

EXTENSION
[Magento 2 Extension Workflow](#)

Configuration Fields

This reference lists the settings exposed by `mageb2b/workflow` in Magento Admin.

Configuration paths are included for controlled deployments and `config:set`. Use Magento Admin for normal changes so field validation and scope inheritance still apply. The extension status display is not listed because it reports installation state rather than a configurable value.

General Settings

Field	Configuration path	Input	Scope
Enable Workflow Engine	<code>workflow/general/enabled</code>	Select	Default

Runtime Settings

Field	Configuration path	Input	Scope
Default Timeout (seconds)	<code>workflow/runtime/default_timeout_seconds</code>	Text	Default
Max Retries	<code>workflow/runtime/max_retries</code>	Text	Default
Max Execution Steps	<code>workflow/runtime/max_execute_steps</code>	Text	Default
Max Simulation Steps	<code>workflow/runtime/max_simulation_steps</code>	Text	Default
Resume Due Batch Size	<code>workflow/runtime/resume_due_batch_size</code>	Text	Default
Max Trigger Chain Depth	<code>workflow/runtime/max_trigger_chain_depth</code>	Text	Default

Webhook Settings

Field	Configuration path	Input	Scope
Max Request Bytes	<code>workflow/webhook/max_request_bytes</code>	Text	Default

Field	Configuration path	Input	Scope
Max Response Bytes	<code>workflow/webhook/max_response_bytes</code>	Text	Default
Max Webhook Retries	<code>workflow/webhook/max_retries</code>	Text	Default
Max Webhook Timeout (seconds)	<code>workflow/webhook/max_timeout_seconds</code>	Text	Default
Allowed HTTP Methods	<code>workflow/webhook/allowed_http_methods</code>	Text	Default
Allowed Hosts	<code>workflow/webhook/allowed_hosts</code>	Text	Default
Max Payload Fields	<code>workflow/webhook/max_payload_fields</code>	Text	Default
Signature TTL (seconds)	<code>workflow/webhook/signature_ttl_seconds</code>	Text	Default
Signature Clock Skew (seconds)	<code>workflow/webhook/signature_skew_seconds</code>	Text	Default
Nonce TTL (seconds)	<code>workflow/webhook/signature_nonce_ttl_seconds</code>	Text	Default

Expression Engine

Field	Configuration path	Input	Scope
Enable Expressions	<code>workflow/expression/enabled</code>	Select	Default

Notifications

Field	Configuration path	Input	Scope
Enable Task Notifications	<code>workflow/notifications/enabled</code>	Select	Default

Condition Models

Field	Configuration path	Input	Scope
Enable Flat Models	<code>workflow/condition_model/enable_flat_models</code>	Select	Default
Flat Model Prefixes	<code>workflow/condition_model/flat_model_prefixes</code>	Text	Default

Import / Export

Field	Configuration path	Input	Scope
Allow Overwrite on Import	<code>workflow/import_export/allow_overwrite</code>	Select	Default
Max Workflow Import Size (MiB)	<code>workflow/import_export/max_import_size_mb</code>	Text	Default